CC Pilot™ XS

MiscPortIO API description







Table of Contents

| Introduction | 3 |
|---------------------------------|---|
| Purpose | |
| References | |
| History | |
| MiscPortIO Services | |
| Summary of interface functions | 4 |
| MiscPortIOConnect | |
| MiscPortIORead | 5 |
| Configuration common | 5 |
| Configuration (Windows 2000/XP) | 6 |
| Configuration (Windows CE) | 7 |

Introduction

Purpose

This document describes the software interface to the MiscPortIO API.

References

_

History

| Rev | Date | Author | Remarks |
|-----|------------|------------------|----------------|
| 1.0 | 08-04-15 | Lars Gustafsson | First version. |
| 1.1 | 2008-06-26 | Tobias Andersson | Minor changes |

MiscPortIO Services

The MiscPortIO API enables access to the three digital IO-pins of the Misc port of the CC Pilot XS. There are 3 possible configurations of the CC Pilot XS. The first one has no IO-pins. The second one has two IO-pins and the third one has three IO-pins. If you try to read any of the pins 6, 7, 8 of the Misc-port which are not IO-pins you will consistently get the same reading every time.

Summary of interface functions.

MiscPortIOConnect Connetcs to the IO-Port. You only need to call this

function once.

MiscPortIORead Reads out the value of the IO-channel specified by

the input parameter "channel".

MiscPortIOConnect

Description

MiscPortIOConnect has to be called before trying to read the value of a pin with MiscPortIORead. You don't have to call MiscPortIOConnect before every reading attempt. It should only be called once.

Include files

#include "MiscPortIO.h"

Syntax

```
extern "C" __declspec(dllexport)
short __stdcall MiscPortIOConnect()
```

Parameters

-

Return value

1 means success. 0 means failure.

Restrictions (Windows 2000/XP)

-

Restrictions (Windows CE)

-

Example

-

MiscPortIORead

Description

Reads the IO-pin specified by the input parameter.

Include files

#include "MiscPortIO.h"

Syntax

```
extern "C" __declspec(dllexport)
short __stdcall MiscPortIORead(short channel)
```

Parameters

channel

Specifies which channel to use. Possible values are 1, 2 and 3.

Return value

- 1 IO-pin pulled high (+24 volt) or is left unconnected.
- 0 IO-pin pulled low (GND)

Observe that the IO-pins are internally pulled up, so the default value is 1.

Restrictions (Windows 2000/XP)

_

Restrictions (Windows CE)

_

Example

```
short ch1;
MiscPortIOConnect();
ch1=MiscPortIORead(1);
```

Configuration common

Summary of common configuration values

| Name: 1) | Type: | Description: |
|----------|-------|--------------|
| | | |

¹ Values in bold are required.

Configuration (Windows 2000/XP)

Summary of Windows 2000/XP configuration values

| Name: | Type: | Description: |
|-------|-------|--------------|
| | | |

Configuration (Windows CE)

Summary of Windows CE configuration values

| Name: ²⁾ | Type: | Description: |
|---------------------|-------|--------------|
| | | |

² Values in bold are required